

---

# **django-auth-iam Documentation**

***Release 0.1.2***

**Michael Budde**

**Aug 02, 2017**



---

## Contents

---

<b>1 Installation</b>	<b>1</b>
<b>2 Usage</b>	<b>3</b>
<b>3 Settings</b>	<b>5</b>
<b>4 API</b>	<b>7</b>
<b>5 Indices and tables</b>	<b>9</b>
<b>Python Module Index</b>	<b>11</b>



# CHAPTER 1

---

## Installation

---

`django-auth-iam` can be installed with pip:

```
$ pip install django-auth-iam
```

Your Amazon credentials need to be specified in a configuration file that looks like this:

```
[Credentials]
aws_access_key_id = AKEIAJLXJFEXAMPLE
aws_secret_access_key = TLJASY/(ASF+fasdAJIdfWLsJfljaeisljae

[DB]
db_name = my_example_user_domain
```

Users will be stored in SimpleDB in the domain specified by `db_name`. This file can be saved where ever you want. To tell `boto` where it can find this file you need to set the `BOTO_CONFIG` environment variable. This can be done in your `settings.py` file:

```
import os
os.environ['BOTO_CONFIG'] = '/path/to/your/boto.cfg'
```

In your Django configuration you also need to set `AUTHENTICATION_BACKEND`:

```
AUTHENTICATION_BACKEND = (
    'django_auth_iam.backends.AmazonIAMBackend'
)
```

## Requirements

`django_auth_iam` currently depends on the development version of `boto`. You can install this with the following command:

```
$ pip install -e git+git://github.com/boto/boto.git#egg=boto
```

# CHAPTER 2

---

## Usage

---

### Creating users

`django_auth_iam` is not integrated with the Django admin interface. You can instead use a python shell or script to create your users. You can start a python shell with `python manage.py shell`:

```
>>> from django_auth_iam.models import User
>>> User.create('user1', 'password')
User<...>
>>> User.create('user2', 'foo1234')
User<...>
>>> user = User.get_by_username('user1')
>>> user.delete()
```

Passwords are automatically hashed before they are stored. To change a users password you can use the method `change_password()`:

```
>>> user = User.create('testuser', 'pass')
>>> user.password == 'pass'
True
>>> user.change_password('pass', 'spam')
>>> print user.password
$2a$12$hmYnBI/VdPjxZep1lbIcLoBBlN.LYYXRanL/1AMYlaJeIn30aBOjo
>>> user.password == 'spam'
True
```



# CHAPTER 3

---

## Settings

---

django-auth-iam has the following settings that control how it works.

### IAM\_USER\_CLASS

**Default** 'django\_auth\_iam.models.User' (django\_auth\_iam.models.User)

Controls what class that is used when instanciating a IAM user object. This should either be the default value or point a subclass of the default class. You can use this to add extra attributes to your user model:

```
import django_auth_iam.models
from boto.sdb.db.property import *

class MyUser(django_auth_iam.models.User):
    favorite_color = StringProperty()
```

And in your settings.py:

```
IAM_USER_CLASS = 'myapp.models.MyUser'
```

#### See also:

The API documentation for boto contains the documentation of the different property types.



# CHAPTER 4

---

API

---

## Models

## Utilities

`django_auth_iam.utils.encrypt_key(plain, password)`

`django_auth_iam.utils.decrypt_key(cipher, password)`



# CHAPTER 5

---

## Indices and tables

---

- genindex
- modindex
- search



---

## Python Module Index

---

### d

`django_auth_iam.models`, [7](#)  
`django_auth_iam.utils`, [7](#)



## D

decrypt\_key() (in module django\_auth\_iam.utils), [7](#)  
django\_auth\_iam.models (module), [7](#)  
django\_auth\_iam.utils (module), [7](#)

## E

encrypt\_key() (in module django\_auth\_iam.utils), [7](#)